


Disclaimer

This Configuration Guide is designed to assist members to enhance their skills in particular technology area. While every effort has been made to ensure that all material is as complete and accurate as possible, the enclosed material is presented on an "as is" basis. Neither the authors nor Forum assume any liability or responsibility to any person or entity with respect to loss or damages incurred from the information contained in this guide. This configuration guide was developed by Forum. Any similarities between material presented in this configuration guide and any other material is completely coincidental.



|||| www.rstforum.net

Task 1: BASIC OSPF and MPLS setup

Configure OSPF and MPLS on all PE-routers and P-router

Step 1. Configure following on respective P and PE routers:

```
PE2 Router Initial Config:
                                              PE3 Router Initial Config:
hostname PE2
                                              hostname PE3
ip cef
                                              ip cef
mpls label protocol ldp
                                              mpls label protocol ldp
                                              no tag-switching ip propagate-ti
no tag-switching ip propagate-ttl
interface Loopback0
                                              interface Loopback(
                                              ip address 192.168.3.3
ip address 192.168.3.2 255.255.255.255
                                              interface FastEthernet0/0
interface FastEthernet1/0
                                              description **link_to_P**
description **link_to_P**
                                               ip address 192.168.3.13 255.255.255.252
ip address 192.168.3.18 255.255.255.252
tag-switching ip
                                               tag-switching ip
no shutdown
                                               no shutdown
interface Serial2/0
                                              interface Serial2/0
                                              description **link_to_B1**
description **link_to_A2**
ip address 150.1.31.5 255255.25
                                              ip address 150.1.32.9 255.255.255.252
no shutdown
                                              no shutdown
interface Serial2/1
                                              interface Serial2/1
description **link_to_B1**
                                              description **link_to_A1**
ip address 150.1.32.1 255.255.255.252
                                              ip address 150.1.31.1 255.255.255.252
no shutdown
                                              no shutdown
interface Serial2/2
                                              interface Serial2/2
description **link_to_A1**
                                              description **link_to_B2**
ip address 150.1.31.9 255.255.255.252
                                              ip address 150.1.32.5 255.255.255.252
no shutdown
                                              no shutdown
```

```
router ospf 64
                                              router ospf 64
log-adjacency-changes
                                              log-adjacency-changes
network 192.168.0.0 0.0.255.255 area 0
                                              network 192.168.0.0 0.0.255.255 area 0
end
                                              end
P Router Config:
hostname P
ip cef
mpls label protocol ldp
no tag-switching ip propagate-ttl
interface Loopback0
ip address 192.168.3.5 255.255.255.255
interface FastEthernet0/0
description **link_to_PE3**
ip address 192.168.3.14 255.255.255.2
tag-switching ip
no shutdown
interface FastEthernet1/0
description **link_to_PE
ip address 192.168.3.17
                            255.255.252
tag-switching ip
no shutdown
router ospf 64
log-adjacency-changes
network 192.168.0.0 0.0.255.255 area 0
end
```

```
A2 Router Initial Config:
                                              B1 Router Initial Config:
hostname A2
                                              hostname B1
interface Loopback0
                                              interface Loopback0
ip address 203.1.0.2 255.255.255.255
                                              ip address 203.2.0.1 255.255.255.255
interface Loopback1
                                              interface Loopback1
ip address 203.1.2.1 255.255.255.0
                                              ip address 203.2.1.1 255.255.255
interface Serial2/0
                                              interface Serial2/0
                                              ip address 150.1.32.10 255.255.255.252
ip address 150.1.31.6 255.255.255.252
clock rate 64000
                                              clock rate 64000
no shutdown
                                              no shutdown
                                              interface Serial2
end
                                              ip address 150.1.32.2 255.255.255.252
                                               clock rate 64000
                                               o shutdown
                                              end
A1 Router Initial Config:
                                              B2 Router Initial Config:
hostname A1
                                              hostname B2
interface Loopback@
                                              interface Loopback0
ip address 203.1.1.1 255.255.255.0
                                              ip address 203.2.0.2 255.255.255.255
interface Loopback1
                                              interface Loopback1
ip address 203.1.0.1 255.255.255.255
                                              ip address 203.2.2.1 255.255.255.0
interface Serial2/1
                                              interface Serial2/2
ip address 150.1.31.2 255.255.255.252
                                              ip address 150.1.32.6 255.255.255.252
clock rate 64000
                                              clock rate 64000
no shutdown
                                              no shutdown
```

```
interface Serial2/2
ip address 150.1.31.10 255.255.252
clock rate 64000
no shutdown
!
end
```

<u>Task 2: Configure Multi-protocol BGP</u>Configure multi-protocol BGP between provider-edge (PE) routers.

Step 1 Enable BGP sessions on all PE routers in your Service Provider backbone. **Step 2** Activate VPNv4 BGP sessions between all PE routers in your Service Provider backbone.

Configure the following on PE2 router:

PE2(config)#

```
neighbor 192.168.3.3 remote-as 3
neighbor 192.168.3.3 update-source Loopback0
!
address-family ipv4
no auto-summary
no synchronization
neighbor 192.168.3.3 activate
network 192.168.3.2 mask 255.255.255.255
exit-address-family
!
address-family vpnv4
neighbor 192.168.3.3 activate
neighbor 192.168.3.3 send-community extended
exit-address-family
```

```
Configure following on PE3 router:
PE3(config)#
router bgp 3
 bgp log-neighbor-changes
 neighbor 192.168.3.2 remote-as 3
 neighbor 192.168.3.2 update-source Loopback0
 address-family ipv4
 no auto-summary
 no synchronization
 neighbor 192.168.3.2 activate
 network 192.168.3.3 mask 255.255.255.255
 exit-address-family
 !
 address-family vpnv4
 neighbor 192.168.3.2 activate
 neighbor 192.168.3.2 send-community extended
 exit-address-family
```

Task 3: Design your VPN Solution Create the virtual private network (VRF) on provider

```
edge (PE2):PE2(config)#
ip vrf a
rd 3:1
route-target both 3:1
!
ip vrf a_central
rd 3:11
route-target both 3:1
poute-target both 3:30
!
ip vrf b_central
rd 3:21
route-target both 3:2
route-target both 3:30
```

```
Create the virtual private network (VRF) on provider edge (PE3):
PE3(config)#
ip vrf a_central
 rd 3:11
 route-target both 3:1
 route-target both 3:30
ip vrf b
rd 3:2
route-target both 3:2
ip vrf b_central
rd 3:21
route-target both 3:2
route-target both 3:30
```

Task 4: Create VRFs for A2, B1, A1 and B2 Attack the provider edge-to-customer edge (PE-CE) link to the newly created VRFs with the following commands on PE2:PE2(config)#

```
interface Serial2/0
ip vrf forwarding a
ip address 150.1.31.5 255.255.255.252
interface Serial2/1
ip vrf forwarding b_central
ip address 150.1.32.1 255.255.255.252
interface Serial2/2
ip vrf forwarding a_central
ip address 150.1.31.9 255.255.255.252
```

Note: "ip vrf forwarding name" command removes the IP address from interface, so IP address need to be re-configured.

Attach the PE-CE link to the newly created VRFs with the following commands on PE3:

```
PE3(config)#

interface Serial2/0

ip vrf forwarding b_central

ip address 150.1.32.9 255.255.252

!

interface Serial2/1

ip vrf forwarding a_central

ip address 150.1.31.1 255.255.252

!

interface Serial2/2

ip vrf forwarding b

ip address 150.1.32.5 255.255.252
```

Task 5: Configure BGP on A1, B1 and A2, B2

The following commands need to be entered on the A1 router:

A1(config)#

```
router bgp 2
neighbor 150.1.31.1 remote-as 3
neighbor 150.1.31.1 allowas-in
neighbor 150.1.31.9 remote-as 3
neighbor 150.1.31.9 allowas-in
redistribute connected
```

The following commands need to be entered on the B1 router:

B1(config)#

```
router bgp 4
neighbor 150.1.32.1 remote-as 3
neighbor 150.1.32.1 allowas-in
neighbor 150.1.32.9 remote-as 3
neighbor 150.1.32.9 allowas-in
redistribute connected
```

```
The following commands need to be entered on the A2 router:

A2(config)#
router bgp 2
neighbor 150.1.31.5 remote-as 3
neighbor 150.1.31.5 allowas-in
redistribute connected

The following commands need to be entered on the B2 router:

B2(config)#
router bgp 4
neighbor 150.1.32.5 remote-as 3
neighbor 150.1.32.5 allowas-in
redistribute connected
```

Task 6: Configure New VRFs For A1 and B1/Re-establish BGP Routing

The following commands need to be entered on PE2:

PE2(config)#

```
router bgp 3
address-family ipv4 vrf b_central
neighbor 150.1.32.2 remote-as 4
neighbor 150.1.32.2 activate
neighbor 150.1.32.2 as-override
exit
address-family ipv4 vrf a_central
neighbor 150.1.31.10 remote-as 2
neighbor 150.1.31.10 activate
neighbor 150.1.31.10 as-override
exit
address-family ipv4 vrf a
neighbor 150.1.31.6 remote-as 2
neighbor 150.1.31.6 activate
```

exit The following commands need to be entered on PE3: PE3(config)# router bgp 3 address-family ipv4 vrf b_central neighbor 150.1.32.10 remote-as 4 neighbor 150.1.32.10 activate neighbor 150.1.32.10 as-override exit address-family ipv4 vrf b neighbor 150.1.32.6 remote-as 4 neighbor 150.1.32.6 activate neighbor 150.1.32.6 as-override address-family ipv4 vrf a_central neighbor 150.1.31.2 remote-as 2 neighbor 150.1.31.2 activate

neighbor 150.1.31.2 as-override

exit